UPGRADING GUARDIAN APP CAM 24/25/26 FIRMWARE

Overview

To upgrade the App Cam 24/25/26 firmware, you will need to download the upgrade file from the Uniden website (www.uniden.com.au) to your computer.

Instructions:

- 1. Disconnect the power from your App Cam.
- 2. Download the firmware to your computer.



- 3. Unzip the file to a folder on your computer.
- 4. Insert the microSD card into your computer (an adapter may be necessary).
- 5. Copy the firmware to the root directory of your microSD card.
- 7. Eject the microSD card and place into your AppCam.
- 8. Connect the power to your App Cam.
- 9. Power up the camera and wait around 3 minutes until camera green LED starts flashing slowly. Do not attempt to power off the camera at any stage.
- 10. The App Cam will install the firmware.
- 11. App Cam will reboot after firmware upgrade completed.
- 12. Remove the registered DID on the mobile application if it was set up previously.
- 13. User will need to reset the system to connect camera to Wi-Fi and Internet.
- 14. When the setup is finish, go to live view to make sure the connection is good.
- 15. You should able to receive push notification when the camera detects motion.

Any further settings, please refer to the full Owner's Manual on Uniden website.

